

## H305

## Extended Mode Secure Bulk File Transfer (BFX™) for Unisys OS2200 Systems

Release 1.3.7

Memo to Users

November 6, 2020

© 2017-2020 Network Executive Software, Inc. 6450 Wedgwood Rd N Ste 103 Maple Grove, MN 55311

# Introduction

This memo provides supplementary and release-dependent information to users and documents any changes to the Software Reference Manual before a new revision is published.

It should be reviewed carefully prior to installation of the product.

This new release of H305 is a functionally equivalent product but is NOT compatible or interoperable to the current releases of H301/H301L, or H301e.

#### **New Features**

This release is a maintenance release for a the secure BFX product (H305) on the Unisys platform.

This product which is functionally equivalent to H301/H301L/H301e, however, it is not compatible or interoperable with any non-secure NetEx products. This product requires H304 (Secure NetEx/IP) and will not interoperate with H300IPC/H300e.

Enhancements were made to the User modules.

Additional support to pad ASCII records to a full word on DiskSec device type files.

For updates, refer to the Update Summary for details.

The following parameters have changed from usage in H301/H301L releases as noted:

Command	Default	Used By
BMOD		Unsupported – IGNORED
BPARM		Unsupported – IGNORED
CHKSUM		Unsupported – ERROR
CLOSE		Deprecated – IGNORED
HOBOPT		Unsupported – ERROR
JFILE		Unsupported – ERROR
JFLAG		Unsupported – ERROR
KEYVAL		Unsupported–ERROR
NOCLOSE		Deprecated – IGNORED
NOCR		Silently ignored
NOCRLF		Silently ignored
NOLF		Silently ignored
RATE		Deprecated – IGNORED
RESTORE		Unsupported – ERROR
RPARM	(blanks)	Silently ignored
SENDJB		Unsupported – ERROR
TIMEFL		Unsupported – ERROR
USE_NAME		Unsupported – ERROR

#### **Release 1.3.7 Updates**

8805	rbm fails compare on 86 character records
8824	DECODE EXIT and TLBL messages during tape transfer
8825	Missing 220I and 101I messages for 2nd file
8826	BFXRBM send and receive record counts differ
8830	SPERRY mode aborts multi-reel transfer
8832	RBM mode extra end of file messages and lost last byte
8836	H305 Messages differ from H301
8848	MODE=OCTET aborts multi-reel transfer
8849	block module ignores fatal messages from remote All platform common code fix
8851	HOBCHECK warnings using H305 that do not appear with H301
8853	I/O error, RC=19043 when sending a MODE=BIT tape
8854	BFX901F Bit-string record size must be a sector multiple
8857	typo in BFX945 message
8866	TSB606 message in H301L changed to TSB607 in H305
8893	Retry Netex 3390 error for conntime (prevent denial of service)
8896	many GOING MULTIREEL messages seen in octet transfer

8915 H305 RBM last character mismatch

## **Release 1.3.6 Updates**

- 8809 "File specified is not on tape" message when sending a disk file
- 8812 Accept validation errors in eof lablels
- 8814 Check if room in network block using the larger of rparm->recsize or rmaxl to avoid NRB-STAT=3005 when using MODE=OCTET
- 8818 bigblock sender/receiver report RMAXL in different formats

### **Release 1.3.5 Updates**

- 8755 BFX121S after the file is sent
- 8766 Tape compare fails due to different size records
- bfxrbm, bfxoct, bigblk, and sendrev prints a authorization for labels tsb612 tsb613 tsb614
- 8806 TSB721 produced in error

## **Release 1.3.4 Updates**

8403 TSB602I Missing Tape Serial Number
8719 RBM character mode transfers stall with multi-volume tape
8734 verify-test uses secure data when non-secure is selected
8736 Enhance processing of record headers
8747 "END OF BFXxx EXECUTION" message not output as expected
8752 MODE=OCTET unexpected messages
8757 29009 error is encountered at end of file Missing error message rlen>rxmal
8758 sendrec transfers 1 file when sl tape, not authozized for labels
8762 bigblk does not use RMAXL if defined – Works differently than H301L

## **Release 1.3.3 Updates**

8718 BFX210S & TSB719E, cannot open JOBFILE and format-A tape needed 8729 HOBCHECK warnings using H305 that do not appear with H301

## **Release 1.3.2 Updates**

8678 Duplicate comapi use statement in links

8681 bfxoct sending partial blocks

8689 Secure BFX SENDER/RECVER and multi-file tapes

8671 Unisys userid can be up to 13 including null. Connect has an 8 character limit

## **Release 1.3.1 Updates**

- 8426 MODE=OCTET Input Reel Positioning error
- 8427 Unable to terminate BFXTI on bad IP address
- 8575 Secure mode initial performance improvements
- 8608 BFX OCTET transfer need to validate the reblocking of records.
- 8613 USSENDER USRECVER errors in user mods
- 8633 H305 missing RTLVL in edit TCPCFG sections
- 8668 BFXJS attempts to open a file already opened

### **Release 1.3 Updates**

- 8234 JSAUTH failure when H624 submitting job
- 8303 SET RMAXL DEFAULT for TRACKIO

- 8356 JOBFile does not need to cycle
- 8403 TSB602I Missing Tape Serial Number
- 8404 BFX realtime support for ,f on execute option -Unisys
- 8406 Data counts differ from H301
- 8462 User request for a BFXJS term command
- 8467 mode = ascii invalid
- 8469 Need to terminate bfxjs on nrb=3911 error loading cctable
- 8490 Move databuffers to program memory, messages still in activity buffers
- 8498 Dash not allowed as token
- 8509 Data truncated without error when RMAXL is smaller than record size
- 8522 Dynamically Modify Remote Host
- 8523 Manual has a typo for the description of the SECHOST and NOSECHOST
- 8544 BFX message values truncate at '%'

#### **Release 1.2 Updates**

- 8044 SNX log level is uninitialized in trol record
- 8086 Support Legacy BFX Products with Secure BFX via Secure TNP
- 8091 Provide consistent Keywords and same functionality for security controls
- 8120 BFXJS must verify userid length in connect data
- 8129 Use BFX message format for Secure NetEx messages
- 8155 MJSEC and NOMJSEC are BFXTI only
- 8192 JSAUTH failure uses incorrect buffer size
- 8200 MDSEC sets NOMDSEC
- 8203 BFXJS does not reset the JSAUTH userid field
- 8206 Intermittent BFX211 error "Cannot open output file jobstart, RC=1."

#### **Release 1.1 Updates**

- 7936 Add message BFX930I transferred nnnKB in nnn msecs = nnn KB/sec
- 7932 Allow 13 character in file name if 13 "."
- 7933 BFX399W Warning tape assigned Format-A
- 7984 BFX407E Message shows entered parameter not Maximum length
- 7931 BFXTRCFG contains TIMEOFFER which is not a BFXTR parameter
- 7903 Rename global config files SBFXTICFG & SBFXTRCFG
- 7934 RMAXL should have a default of 28

- 7935 Time stamp needs to include milliseconds on Unisys
- 7937 TSB710I message on sender and receiver when CFMT tapes are used
- 7995 error when trying to send a file